### Rules for smartphone users in Roaming!

# Switching to a partner network manually in roaming:

#### Android:

- 1. Settings Other or More networks\* Mobile networks select dual network mode WCDMA/GSM or GSM/UMTS(3G).
- 2. Wait for a welcome SMS from Kcell.
- 3. Use the manual network selection mode to select a recommended network which you can find in SMS from Kcell (if necessary, try again).
- 4. If connection is lost, repeat the above steps.

### IPhone:

- 1. Check if 3G mode is enabled: Settings Cellular Voice / Data 3G. (\*For iOS 8.1 or below: Settings Cellular Enable 3G).
- 2. Wait for a welcome SMS from Kcell.
- 3. In the manual network selection mode: Settings Carrier Automatic select the recommended operator, which you can find in SMS from Kcell (if necessary, try again).
- 4. If you fail to connect to the recommended network, disable 3G: Settings Cellular Voice/Data 2G (\*For iOS 8.1 or below: Settings Cellular Disable 3G), restart your phone and try manual network selection again (if necessary, repeat these steps several times).

# If you want to use mobile internet in roaming:

- 1. Check out data roaming rates before going abroad.
- 2. Set "Internet" in APN field in your Settings and enable mobile data:

#### Android:

- Settings Other networks or More\* Mobile networks APN New APN (name: internet, APN: internet,
  APN type: default)
- Settings Other networks or More\* Mobile networks Mobile data or Data roaming enable.

# IPhone:

- Settings Cellular Cellular data Cellular data network. (APN: internet)
- Settings Cellular Cellular data enable Data roaming enable.
  - 3. Turn off automatic applications updates in order to prevent unnecessary data usage.

### Android:

Play Store – open the popup menu (in the upper left corner of the screen) – Settings – select Auto-update apps over Wi-Fi only.

#### **IPhone**

Settings – iTunes Store App Store – Automatic downloads (disable all) and disable below updates over cellular data "use cellular data".

# If you do not want to use mobile internet:

#### Android:

- Settings Data usage\* Mobile data (deselect).
- 2. Settings Other networks or More \* Mobile networks Data roaming (deselect).

### IPhone:

- 3. Settings Cellular Data roaming disable.
- 4. Settings Cellular Wi-Fi Assist off (Version IOS 9)

### Important!

Disable automatic download of video, audio, photo in WhatsApp, Viber.

<sup>\*</sup>Menus and options may vary depending on phone model.